## **Enable Strict Transport Security In Apache Virtual Host for Nextcloud**

## **Enable HTTP Strict Transport Security**

While redirecting all traffic to HTTPS is good, it may not completely prevent man-in-the-middle attacks. Thus administrators are encouraged to set the HTTP Strict Transport Security header, which instructs browsers to not allow any connection to the Nextcloud instance using HTTP, and it attempts to prevent site visitors from bypassing invalid certificate warnings.

This can be achieved by setting the following settings within the Apache VirtualHost file:

This example configuration will make all subdomains only accessible via HTTPS. If you have subdomains not accessible via HTTPS, remove includeSubDomains. Consider how this would affect integration with OnlyOffice Document Server hosted on a subdomain of the NextCloud domain, unless the subdomain is added to or included in the LetsEncrypt SSL certificate.

IMPORTANT: This requires the mod headers extension in Apache.

Let's see how to enable headers module using a2enmod

How to Enable mod\_headers in Apache Ubuntu Here's how to enable mod\_headers in Apache Ubuntu / Debian.

1. Install mod\_headers If you want to install Apache module such as mod\_headers, you need to issue the a2enmod command

```
$ sudo a2enmod <module_name>
<code>
Open terminal and run the following command.
<code>
$ sudo a2enmod headers
```

\$ sudo a2enmod headers

Result:

```
Enabling module headers.
To activate the new configuration, you need to run:
```

\$

systemctl restart apache2

2. Restart Apache web server for changes to take effect

\$ sudo systemctl restart apache2

OR

\$ sudo service apache2 restart

Result:

3. Check if mod\_headers is working. You can easily check if mod\_headers is enabled by running the following command

\$ apachectl -M | headers

OR

\$ apache2ctl -M | grep headers

If you see the following output, it means mod headers is enabled and working.

- \$ headers\_module (shared)
- 4. Disable mod\_headers. If you want to disable/uninstall Apache module such as mod\_headers, you need to issue the a2dismod command
- \$ sudo a2dismod <module\_name>

To disable/uninstall mod headers run the following command.

\$ sudo a2dismod headers

Restart Apache web server to apply changes.

From

https://installconfig.com/ - Install Config Wiki

Permanent link:

https://installconfig.com/doku.php?id=enable\_strict\_transport\_security\_apache\_virtual\_host&rev=1687626641

Last update: 2023/06/24 17:10



https://installconfig.com/ Printed on 2025/12/15 23:47